# datarun Documentation

Release 0.4

**Camille** 

### CONTENTS

1	low to use datarun?	3			
	.1 1- Send data to datarun	3			
	.2 2- Split data into train and test dataset	4			
	.3 3- Send submission on cv fold to be trained on datarun	5			
	.4 4- Get back your predictions	5			
	.5 5- Install new packages on runners	6			
2	Models	7			
3	3 Requests				
	.1 direct requests	9			
	.2 post_api module	12			
4	Deployment	17			
	.1 How to run it locally?	17			
	.2 How to run it on stratuslab openstack?	18			
5	Eests	23			
	.1 for django tests	23			
	.2 for local celery tests	23			
	.3 for tests on stratuslab	23			
6	Now to deal with migrations?	25			
7	7 Indices and tables				
Рy	Python Module Index				
In	x	31			

Datarun goal is to train and test machine learning models. It is a REST API written in Django.


The basic workflow is the following (more details can be found in *How to use datarun?*):

- 1. Data (on which machine learning models are trained and tested) are sent to datarun.
- 2. Models and train and test indices of CV fold are send to datarun, which train and test these models on these indices.
- 3. The resulting predictions can then be requested.

In this documentation, we use the following terminology (which corresponds to the database tables, cf *Models*):

- RawData refers to the data on which machine learning models are trained and tested
- Submission refers to a machine learning model
- Submission on cv fold/SubmissionFold refers to a submission and the indices of train and test of a cv fold.

Datarun is made of a master and datarunners, as represented below:



Contents:

CONTENTS 1

2 CONTENTS

ONE

### **HOW TO USE DATARUN?**

The workflow to use datarun is the following:

### 1- Send data to datarun

The standard format of a data file excepted by datarun is a csv file whose first row contains the feature and target names, each line corresponds to a data sample.

Here is an example of a standard data file:

```
sepal length, sepal width, petal length, petal width, species 5.1, 3.5, 1.4, 0.2, setosa 4.9, 3.0, 1.4, 0.2, setosa 4.7, 3.2, 1.3, 0.2, setosa 4.6, 3.1, 1.5, 0.2, setosa
```

If your data match the standard data file, you need to send:

- the dataset name (for instance if you use databoard, you can use the problem name)
- · your data file
- the name of the target column
- the workflow elements of the problem related to the dataset (for instance feature\_extractor, classifier, ...)

If your data do not match the standard data file, you need to send in addition to above:

- a python file with 5 specific functions (an example of such file is test\_files/variable\_stars/variable\_stars\_datarun.py):
  - prepare\_data(raw\_data\_path)
  - get\_train\_data(raw\_data\_path)
  - get\_test\_data(raw\_data\_path)
  - train\_submission(module\_path, X, y, train\_indices)
  - test\_submission(trained\_model, X, test\_indices)
- possibly other data files (if your data are split in different files).

In both cases, to send your data to datarun, you can use:

- a post request to <master-host>/runapp/rawdata/ (cf *direct requests*, class runapp.views.RawDataList)
- the post\_data function in the module test\_files.post\_api (cf post\_api module)

#### Note for databoard users:

- 1. To prepare data for datarun:
- If they match the standard data file, there is nothing to do.
- If they do not match the standard data file,
  - 1. create a file problems/problem\_name>\_datarun.py which corresponds to the above mentionned python file.
     Functions prepare\_data(raw\_data\_path), get\_train\_data(raw\_data\_path), and

get\_test\_data(raw\_data\_path) are almost exact copies of the same functions defined in databoard/specific/problems/cproblem\_name>.py, except the dependence on raw\_data\_path (which allows datarun to find the data file where it saves it). Be careful to remove all dependencies with databoard module. Functions train\_submission (module\_path, X, y, train\_indices) and test\_submission (trained\_model, X, test\_indices) are exact copies of the same functions defined in the problem workflow (databoard/specific/workflows/<workflow\_name>.py).

- 2. Add in databoard/specific/problems/sproblem\_name>.py a line specifying the above
  mentionned python file and possible other data files. E.g, extra\_files = extra\_files
  = [vf\_raw\_filename, os.path.join(problems\_path, problem\_name,
   'variable\_star\_datarun.py')] (for the variable stars problem).
- 2. To send data to datarun and to split data into train and test dataset, you can use the function send\_data\_datarun of databoard/db\_tools.py, which uses the functions post\_data and post\_split (or custom\_post\_split) of the module test\_files.post\_api of datarun.

This function can be called with fab:

fab send\_data\_datarun:cproblem\_name, <datarun\_master\_url</pre>, <datarun\_password>

# 2- Split data into train and test dataset

If your data match the standard format, you can use:

- a post request to <master-host>/runapp/rawdata/split/ (cf direct requests, class runapp.views.SplitTrainTest)
- the post\_split function in the module test\_files.post\_api (cf post\_api module)

If your data do not match the standard format, you can use:

- a post request to <master-host>/runapp/rawdata/customsplit/ (cf direct requests, class runapp.views.CustomSplitTrainTest)
- the custom\_post\_split function in the module test\_files.post\_api (cf post\_api module)

Note for databoard users: To send data to datarun and to split data into train and test dataset, you can use the function send\_data\_datarun of databoard/db\_tools.py, which uses the functions post\_data and post\_split (or custom\_post\_split) of the module test\_files.post\_api of datarun (cf previous section).

This function can be called with fab:

fab send\_data\_datarun:cproblem\_name, <datarun\_master\_url</pre>, <datarun\_password</pre>

### 3- Send submission on cv fold to be trained on datarun

To send a submission on cv fold, you can use:

- a post request to <master-host>/runapp/submissionfold/ (cf direct requests, class runapp.views.SubmissionFoldList)
- the post\_submission\_fold function in the module test\_files.post\_api (cf post\_api module)

If the associted submission files have already been sent, you'll need to send:

- the id of the associated submission
- the id of the submission on cv fold
- the train and test indices of the cv fold.
  - after compression (with zlib) and base64-encoding if you use a post request
  - the raw indices if you use the post\_submission\_fold function
- the priority level (L for low or H for high) of training this submission on cv fold.
- an indication that you want to force retraining the submission on cv fold even if it already exists (force="submission\_fold" instead of force=None).

If the associated submission files have not been sent, you need to add:

- the id of the associated data. This id can be retrieved using:
  - a post request to <master-host>/runapp/rawdata/ (cf direct requests, class runapp.views.RawDataList)
  - the get\_raw\_data function in the module test\_files.post\_api (cf post\_api module)
- the list of submission files
- an indication that you want to force resending the submission even if its id already exists (force="submission" instead of force=None).

Note for databoard users: To send a submission on cv fold, you can use the function train\_test\_submissions\_datarun of databoard/db\_tools.py (which uses functions from the module test\_files.post\_api of datarun).

This function can be called with fab:

```
fab train_test_datarun:<data_id_datarun>, <datarun_master_url>,<datarun_username>,
<datarun_password>,<problem_name>,<team_name>,<submission_name>(,force=True)
```

The <data\_id\_datarun> is printed when sending data to datarun, or it can be retrieved as mentionned above.

# 4- Get back your predictions

If you want to get all predictions that have not been requested, you can use:

- a post request to <master-host>/runapp/testpredictions/new/ (cf direct requests, class runapp.views.GetTestPredictionNew)
- the get\_prediction\_new function in the module test\_files.post\_api (cf post\_api module)

If you want to get predictions given a list of submission on cv fold ids, you can use:

• a post request to <master-host>/runapp/testpredictions/list/ (cf *direct requests*, class runapp.views.GetTestPredictionList)

• the get\_prediction\_list function in the module test\_files.post\_api (cf post\_api module)

Note for databoard users: To get back predictions, you can use the function  $get\_trained\_tested\_submissions\_datarun$  of databoard/db\_tools.py (which uses functions from the module test\_files.post\_api of datarun).

This function can be called with fab:

# 5- Install new packages on runners

To install a new package {package\_name} on runners (listed in a text file {file\_runner}), go to script\_install directory and run:

```
bash runners_install.sh {file_runner} {package_name}
```

An example of {file\_runner} (which is the file used to deploy runners, see section deployment):

```
134.158.75.112 2 L,celery 360 300
134.158.75.113 3 H 240 200
```


After installing new packages, you must restart runners with:

```
bash runners_restart.sh {file_runner}
```

### **TWO**

### **MODELS**

The database schema is the following:



class runapp.models.RawData(\*args, \*\*kwargs)

### **Parameters**

- name (string) name of the data set
- **files\_path** (*string*) path of file where data are saved
- workflow\_elements (string) list of workflow elements used to solve the RAMP
- column (target) name of the target column

class runapp.models.Submission(\*args, \*\*kwargs)

#### **Parameters**

• databoard\_s\_id (IntegerField(primary\_key=True)) - id of the submission in the db of databoard

- files\_path (CharField(max\_length=200, null=True)) path of submitted files
- raw\_data (ForeignKey(RawData, null=True, blank=True)) associated raw data

class runapp.models.SubmissionFold(\*args, \*\*kwargs)

#### **Parameters**

- databoard\_sf\_id (IntegerField(primary\_key=True)) id of the submission on cv fold in databoard db
- databoard\_s (ForeignKey (Submission, null=True, blank=True))-associated submission
- train\_is (TextField) train indices
- test\_is (TextField) test indices
- **priority** (CharField, choices.) priority to train-test the fold ('L' for low priority, 'H' for high priority)
- full\_train\_predictions (TextField) predictions of the entire train dataset
- **test\_predictions** (*TextField*) predictions of the test dataset
- state (CharField, choices.) TODO, TRAINED, VALIDATED, TESTED, ERROR
- log\_messages (TextField) logs recorded during train and test
- train\_time (FloatField, default=0.) real clock training time
- validation\_time (FloatField, default=0.) real clock validation time
- test\_time (FloatField, default=0.) real clock testing time
- train\_cpu\_time (FloatField, default=0.) training cpu time
- train\_memory peak memory usage during train and test (in kb)
- test\_cpu\_time test cpu time
- **test\_memory** (FloatField, default=0.) peak memory usage durning train and test (in kb)
- new (BooleanField, default=True.) True when it has not already been sent by the API

8 Chapter 2. Models

### THREE

### REQUESTS

You can either make direct requests to the datarun API, or use the post\_api function.

# direct requests

```
class runapp.views.CustomSplitTrainTest(**kwargs)
     Split data set into train and test datasets for custom dataset (when a specific.py was submitted along with raw
     post (request, format=None)
           Split raw data into train and test datasets for custom dataset
              •Example with curl (on localhost):
                   curl -u username:password -H "Content-Type:
                                                                          application/json" -X POST -d
                    '{"raw_data_id": 1}' http://127.0.0.1:8000/runapp/rawdata/customsplit/
                   Don't forget double quotes for the json, simple quotes do not work
              •Example with the python package requests (on localhost):
                   requests.post('http://127.0.0.1:8000/runapp/raw_data/customsplit/',
                                                                                         auth=('username',
                    'password'), json={'raw_data_id': 1})
           — parameters:
              •name: raw_data_id description: id of the raw dataset required: true type: integer paramType: form
class runapp.views.GetTestPredictionList(**kwargs)
     Get predictions of submissions on cv fold given their ids
     post (request, format=None)
           Retrieve predictions (on the test data set) of SubmissionFold instances among a list of id that have been
           trained and tested
              •Example with curl (on localhost):
                   curl -u username:password -H "Content-Type:
                                                                         application/json" -X POST -d
                    '{"list_submission_fold": [1, 2, 10]}' http://127.0.0.1:8000/runapp/testpredictions/list/
                   Don't forget double quotes for the json, simple quotes do not work
              •Example with the python package requests (on localhost):
                   requests.post('http://127.0.0.1:8000/runapp/testpredictions/list/', auth=('username', 'pass-
                   word'), json={'list_submission_fold': [1, 2, 10]})
           — parameters:
```

•name: list\_submission\_fold description: list of submission on cv fold ids required: true type: list paramType: form

response\_serializer: TestPredSubmissionFoldSerializer

```
class runapp.views.GetTestPredictionNew(**kwargs)
```

Get predictions of submissions on cv fold that have not been requested

```
post (request, format=None)
```

Retrieve predictions (on the test data set) of SubmissionFold instances that have been trained and tested and not yet requested. You can specify a given data challenge by posting the raw\_data id.

•Example with curl (on localhost):

```
curl -u username:password -H "Content-Type: application/json" -X POST -d '{"raw_data_id": 1}' http://127.0.0.1:8000/runapp/testpredictions/new/
```

Don't forget double quotes for the json, simple quotes do not work

•Example with the python package requests (on localhost):

```
requests.post('http://127.0.0.1:8000/runapp/testpredictions/new/', auth=('username', 'password'), json={'raw_data_id': 1})
```

- parameters:

•name: raw\_data\_id description: id of the raw dataset from which to get predictions required: false type: integer paramType: form

response\_serializer: TestPredSubmissionFoldSerializer

```
class runapp.views.RawDataList(**kwargs)
```

List all data set or submit a new one

```
get (request, format=None)
```

List all raw dataset

•Example with curl (on localhost):

curl -u username:password GET http://127.0.0.1:8000/runapp/rawdata/

•Example with the python package requests (on localhost):

```
requests.get('http://127.0.0.1:8000/runapp/rawdata/', auth=('username', 'password'))
```

— response\_serializer: RawDataSerializer

```
post (request, format=None)
```

Create a new dataset

You have to post the name of the dataset, the target column, the workflow elements, and the raw data file. If your data file does not match the format expected by datarun (a csv with a first row containing the feature and target column name, and then a row for each sample), you can submit a python file containing three functions: prepare\_data(data\_path), get\_train\_data(data\_path), and get\_test\_data(data\_path)

•Example with curl (on localhost):

```
curl -u username:password -H "Content-Type: application/json" -X POST -d '{"name": "iris", "target_column": "species", "workflow_elements": "classifier", "files": {"iris.csv": 'blablabla', 'specific.py': 'bli'}}' http://127.0.0.1:8000/runapp/rawdata/
```

Don't forget double quotes for the json, simple quotes don't work.

•Example with the python package requests (on localhost):

```
requests.post('http://127.0.0.1:8000/runapp/rawdata/',
                                                                           auth=('username',
                   json={'name': 'iris', 'target_column': 'species', 'workflow_elements': 'classifier', 'files':
                    {'iris.csv': 'bla', 'specific.py': 'bli'}})
           — request_serializer: RawDataSerializer response_serializer: RawDataSerializer
class runapp.views.SplitTrainTest(**kwargs)
     Split data set into train and test datasets for normal dataset
     post (request, format=None)
           Split raw data into train and test datasets for normal dataset
               •Example with curl (on localhost):
                   curl -u username:password -H "Content-Type:
                                                                              application/json" -X
                                                                                                      POST
                                                                             0.7,
                        '{"random_state":
                                                42,
                                                       "held_out_test":
                                                                                    "raw_data_id":
                                                                                                         1}'
                   http://127.0.0.1:8000/runapp/rawdata/split/
                   Don't forget double quotes for the json, simple quotes do not work
               •Example with the python package requests (on localhost):
                   requests.post('http://127.0.0.1:8000/runapp/raw_data/split/', auth=('username', 'password'),
                   json={'random_state': 42, 'held_out_test': 0.7, 'raw_data_id': 1})
            – parameters:
               •name: random_state description: random state used to split data required: false type: integer param-
               Type: form
               •name: held out test description: percentage of the dataset kept as test dataset required: true type:
               float paramType: form
              •name: raw_data_id description: id of the raw dataset required: true type: integer paramType: form
class runapp.views.SubmissionFoldDetail(**kwargs)
     Get a submission on CV fold given its id
     get (request, pk, format=None)
           Retrieve a SubmissionFold instance to check its state
               •Example with curl (on localhost):
                   curl -u username:password GET http://127.0.0.1:8000/runapp/submissionfold/10/
               •Example with the python package requests (on localhost):
                   requests.get('http://127.0.0.1:8000/runapp/submissionfold/10/', auth=('username', 'pass-
                   word'))
           — parameters:
               •name: pk description: id of the submission on cv fold in the databoard db required: true type: interger
               paramType: path
           response_serializer: SubmissionFoldSerializer
class runapp.views.SubmissionFoldLightList(**kwargs)
     To get main info about all submissions on CV fold
     get (request, format=None)
           List main info (id, submission id, state, new) about all submissions on CV fold
               •Example with curl (on localhost):
                   curl -u username:password GET http://127.0.0.1:8000/runapp/submissionfold-light/
```

3.1. direct requests

•Example with the python package requests (on localhost):

```
requests.get('http://127.0.0.1:8000/runapp/submissionfold-light/', auth=('username', 'password'))
```

— response\_serializer: SubmissionFoldLightSerializer

```
class runapp.views.SubmissionFoldList(**kwargs)
```

To get all submissions on CV fold

```
get (request, format=None)
```

List all submission on CV fold

•Example with curl (on localhost):

curl -u username:password GET http://127.0.0.1:8000/runapp/submissionfold/

•Example with the python package requests (on localhost):

```
requests.get('http://127.0.0.1:8000/runapp/submissionfold/', auth=('username', 'password'))
```

- response serializer: SubmissionFoldSerializer

```
post (request, format=None)
```

Create a submission on CV fold (and if necessary the associated submission)

•Example with curl (on localhost):

```
curl -u username:password -H "Content-Type: application/json" -X POST -d '{"databoard_s_id": 1, "files": {"classifier.py": "import sklearn.."}, "train_is": "hgjhg", "raw_data":1, "databoard_sf_id": 11, "test_is": "kdjhLGf2", "priority": "L"}' http://127.0.0.1:8000/runapp/submissionfold/
```

Don't forget double quotes for the json, simple quotes do not work

•Example with the python package requests (on localhost):

```
requests.post('http://127.0.0.1:8000/runapp/submissionfold/', auth=('username', 'password'), json={'databoard_sf_id': 10, 'databoard_s_id': 24, 'raw_data': 8, 'train_is': 'GDHRFdfgfd', 'test_is': 'kdjhLGf2', 'priority': 'L' 'files': {'classifier.py': 'import skle...'}})
```

Possible to force the submission and submission on CV fold (even if the ids already exist) by adding to the data dictionary "force": 'submission, submission\_fold' to resubmit both, or "force": 'submission\_fold' to resubmit only the submission on CV fold

— request\_serializer: SubmissionFoldSerializer response\_serializer: SubmissionFoldSerializer

```
runapp.views.save_files(dir_data, data)
save files from data['files'] in directory dir_data
```

# post\_api module

```
test_files.post_api.custom_post_split (host_url, username, password, raw_data_id)

To split data between train and test on datarun using a specific prepare_data function sent by databoard
```

#### **Parameters**

- host url (string) api host url, such as http://127.0.0.1:8000/ (localhost)
- **username** (*string*) username to be used for authentication

- password (string) password to be used for authentication
- raw\_data\_id (integer) id of the raw dataset on datarun

test\_files.post\_api.get\_prediction\_list(host\_url, username, password, list\_submission\_fold\_id) password,

Get predictions given a list of submission on cv fold ids

#### **Parameters**

- host\_url (string) api host url, such as http://127.0.0.1:8000/ (localhost)
- **username** (*string*) username to be used for authentication
- **password** (*string*) password to be used for authentication
- list\_submission\_fold\_id (list) list of submission on cv fold ids from which we want the predictions

test\_files.post\_api.get\_prediction\_new (host\_url, username, password, raw\_data\_id)

Get all new predictions given a raw data id

#### **Parameters**

- host url (string) api host url, such as http://127.0.0.1:8000/ (localhost)
- **username** (*string*) username to be used for authentication
- password (string) password to be used for authentication
- raw\_data\_id (integer) id of a data set from which we want new predictions

test\_files.post\_api.get\_raw\_data(host\_url, username, password)
Get all raw data sets

#### **Parameters**

- host\_url (string) api host url, such as http://127.0.0.1:8000/ (localhost)
- **username** (*string*) username to be used for authentication
- password (string) password to be used for authentication

test\_files.post\_api.get\_submission\_fold (host\_url, username, password)
Get all submission on cv fold (all attributes)

#### Parameters

- host\_url (string) api host url, such as http://127.0.0.1:8000/ (localhost)
- username (string) username to be used for authentication
- password (string) password to be used for authentication

test\_files.post\_api.get\_submission\_fold\_detail (host\_url, username, password, submission\_fold\_id)

Get details about a submission on cv fold given its id

#### **Parameters**

- host\_url (string) api host url, such as http://127.0.0.1:8000/ (localhost)
- **username** (*string*) username to be used for authentication
- password (string) password to be used for authentication
- submission\_fold\_id id of the submission on cv fold
- submission\_fold\_id-integer

test\_files.post\_api.get\_submission\_fold\_light (host\_url, username, password)
Get all submissions on cv fold only main info: id, associated submission id, state, and new

#### **Parameters**

- host\_url (string) api host url, such as http://127.0.0.1:8000/ (localhost)
- **username** (*string*) username to be used for authentication
- password (string) password to be used for authentication

test\_files.post\_api.post\_data (host\_url, username, password, data\_name, target\_column, work-flow\_elements, data\_file, extra\_files=None)

To post data to the datarun api. Data are compressed (with zlib) and base64-encoded before being posted.

#### **Parameters**

- host\_url (string) api host url, such as http://127.0.0.1:8000/ (localhost)
- **username** (*string*) username to be used for authentication
- password (string) password to be used for authentication
- data\_name (string) name of the raw dataset
- target\_column (string) name of the target column
- workflow\_elements (string) workflow elements associated with this dataset, e.g., feature extractor, classifier
- data\_file (string) name with absolute path of the dataset file
- extra\_files (list of string) list of names with absolute path of extra files (such as a specific.py)

test\_files.post\_api.post\_split (host\_url, username, password, held\_out\_test, raw\_data\_id, random\_state=42)

To split data between train and test on datarun

#### **Parameters**

- host\_url (string) api host url, such as http://127.0.0.1:8000/ (localhost)
- username (string) username to be used for authentication
- password (string) password to be used for authentication
- held\_out\_test (float (between 0 and 1)) ratio of data for the test set
- raw\_data\_id (integer) id of the raw dataset on datarun
- random state (integer) random state to be used in the shuffle split

```
test_files.post_api.post_submission_fold(host_url, username, password, sub_id, sub_fold_id, train_is, test_is, priority='L', raw_data_id=None, list_submission_files=None, force=None)
```

To post submission on cv fold and submission (if not already posted). Submission files are compressed (with zlib) and base64-encoded before being posted.

#### **Parameters**

- host\_url (string) api host url, such as http://127.0.0.1:8000/ (localhost)
- **username** (*string*) username to be used for authentication
- password (string) password to be used for authentication

- **sub\_id** (*integer*) id of the submission on databoard
- **sub\_fold\_id** (*integer*) id of the submission on cv fold on databoard
- train\_is (numpy array) train indices for the cv fold
- test\_is (numpy array) test indices for the cv fold
- priority (string) priority level to train test the model: L for low and H for high
- raw\_data\_id (integer) id of the associated data, when submitting a submission
- list\_submission\_files (list) list of files of the submission, when submitting a submission
- **force** (string) to force the submission even if ids already exist force can be 'submission, submission\_fold' to resubmit both or 'submission, submission\_fold' to resubmit only the submission on cv fold. None by default.

### **FOUR**

### **DEPLOYMENT**

- How to run it locally?
- How to run it on stratuslab openstack?

## How to run it locally?

### 1. Install the application

Clone the project: git clone https://github.com/camillemarini/datarun.git

Install dependencies (might be useful to create a virtual environment before, eg using virtualenv and virtualenvwrapper):

- 1. For numpy, scipy, and pandas (for Unbuntu & Debian users): sudo apt-get install python-numpy python-scipy python-pandas
- 2. pip install -r requirements.txt

Install RabbitMQ (celery broker): sudo apt-get install rabbitmq-server

Install Redis and set it up for our app (celery result backend):

```
sudo apt-get install -y redis-server
pip install redis
sudo sed -i "331a requirepass $DR_DATABASE_PASSWORD" /etc/redis/redis.conf
sudo service redis-server restart
```

### 2. Set up the database

Datarun uses a Postgres database. Before starting, install postgres if needed and create a database with createdb database\_name.

### 3. Define environment variables

- DR\_WORKING\_ENV: PROD for production environment or DEV for development env
- DIR\_DATA: directory where to save data (you must create the folder beforehand)
- DIR\_SUBMISSION: directory where to save submissions (you must create the folder beforehand)
- DR\_DATABASE\_NAME: database name
- DR\_DATABASE\_USER: database user name

- DR\_DATABASE\_PASSWORD: database user password (do not use special characters)
- DR\_EMAIL: email for the platform superuser
- CELERY\_SCHEDULER\_PERIOD: period (in min) at which the scheduler checks new trained models and saves them in the database. Ex: \*/2 for every 2 min.
- RMQ\_VHOST: RabbitMQ vhost name
- IP\_MASTER: ip address of the master, here: localhost

 $If your are using virtual envwrapper, you can store these variables in {\tt \$VIRTUAL\_ENV/bin/postactivate} \\$ 

#### Example:

```
export DR_DATABASE_NAME=datarun
export DR_DATABASE_USER=db_user
export DR_DATABASE_PASSWORD=db_password
export DR_WORKING_ENV=DEV
export DIR_DATA=data_folder
export DIR_SUBMISSION=submission_folder
export RMQ_VHOST=rabbithost
export IP_MASTER=localhost
```

### 4. Apply migrations

Run: python manage.py migrate

### 5. Create a superuser

Run: python manage.py createsuperuser

### 7. Start celery worker and scheduler

#### Set up RabbitMQ:

```
sudo rabbitmqctl add_user $DR_DATABASE_USER $DR_DATABASE_PASSWORD
sudo rabbitmqctl add_vhost $RMQ_VHOST
sudo rabbitmqctl set_permissions -p $RMQ_VHOST $DR_DATABASE_USER ".*" ".*" ".*"
sudo service rabbitmq-server restart
```

Run: bash test\_files/cmd\_workers.sh start 2 1 for 3 workers, of which one is for the scheduler Note: to start one worker, run: celery -A datarun worker -1 info


### 6. Run the server (localhost)

Run: python manage.py runserver

# How to run it on stratuslab openstack?

There are two possibilities:

1. from scratch using an Ubuntu 14.04 image on openstack, or on any other cloud.



2. using images datarun\_master and datarun\_runner on openstack

Note: in both cases, you need a scienceFS account. On your scienceFS disk, create in the root directory a folder called datarun.

### A. Using an Ubuntu 14.04 image

#### A1. Start one instance for the master and as many instances as you want for the runners.

Use Ubuntu v14.04 images. For the master, use at least an os.2 flavor (4G RAM).

### A2. Go to the script\_install directory and stay there while configuring the master and runners.

#### A3. Configure the master

- On your local computer, create a file called env.sh (do not change this name) with the content below. Do not forget to change the values and be careful **not to commit this file**:-) And **do not add comments to the file**.
  - SCIENCEFS\_LOGIN is your scienceFS login.
  - SCIENCEFS\_DATARUN is the name of the directory on your scienceFS disk (write only the name of the
    directory located in your scienceFS home, no need for /, e.g. datarun), make sure that it has been
    created on the sciencefs disk beforehand.
  - DR\_DATABASE\_NAME, DR\_DATABASE\_USER, DR\_DATABASE\_PASSWORD are the database settings, you can use what you want, e.g. datarun\_db, toto, secret\_password
  - USER\_LOGIN, USER\_PASSWORD, and DR\_EMAIL are username, password and email of a datarun superuser. You can use this user credentials to make requests to the datarun API and to connect to flower. You can create other users once you've deployed the app. You can choose what you want for these settings.
  - DIR\_DATA and DIR\_SUBMISSION are the path to folders where the data and submission are saved. It has to start with /mnt/datarun, e.g. /mnt/datarun/data and /mnt/datarun/submission.
  - CELERY\_SCHEDULER\_PERIOD specifies the period in min \*/<min> at which predictions computed
    by runners are put back in the database. You can use \*/2.
  - RMQ\_VHOST is the name of the Vhost for RabbitMQ. You can use what you want, e.g. datarun.
  - IP\_MASTER is the IP of the master, you can let it as it is, it is a command that get the IP of the master.

```
export SCIENCEFS_LOGIN='login_for_scienceFS_account'
export SCIENCEFS_DATARUN='path_of_sciencefs_disk'
export DR_DATABASE_NAME='database_name'
export DR_DATABASE_VSER='database_user'
export DR_DATABASE_PASSWORD='database_password'
export USER_LOGIN='user_name'
export USER_PSWD='user_password'
export DR_EMAIL='mail@emailworld.com'
export DIR_DATA='/mnt/datarun/data'
export DIR_SUBMISSION='/mnt/datarun/submission'
export CELERY_SCHEDULER_PERIOD='*/2'
export RMQ_VHOST='rabbitMQ_vhost_name'
export IP_MASTER=$(/sbin/ifconfig eth0 | grep "inet addr" | awk -F: '{print $2}' | awk '{print $2}'
```

• Run:

```
bash scp_master_stratuslab.sh master_address scienceFS_private_key
```

with master\_address being the master server address (e.g., onevm-81.lal.in2p3.fr) and scienceFS\_private\_key being the file name (with absolute path) of the private key to connect to ScienceFS account. This will scp to the master some files that are needed to configure the master.

• Ssh to the instance and run:

```
bash deploy_master_stratuslab.sh
source ~/.bashrc
```

• Once you've checked that the app is running (going to <master\_address>/admin for instance), do not forget to change the Django setting DEBUG to False and add the server name (<IP\_MASTER>) in ALLOWED\_HOSTS (preceded with a dot). In /home/datarun/datarun/settings.py:

```
DEBUG = False
ALLOWED_HOSTS = ['.<IP_MASTER>']
```

• Restart Apache: sudo service apache2 restart

### A4. Configure runners

• On your local computer in the folder script\_install, create a file called env\_runner.sh (be careful to use the name env\_runner.sh). Do not forget to change the values and be careful not to commit this file:-) And do not add comments to the file. Make sure that the directory SCIENCEFS\_DATARUN has been created on the sciencefs disk beforehand.

```
export SCIENCEFS_LOGIN='login_for_scienceFS_account'
export SCIENCEFS_DATARUN='path_of_sciencefs_disk'
export DR_DATABASE_USER='database_name'
export DR_DATABASE_PASSWORD='database_password'
export DIR_DATA='/mnt/datarun/data'
export DIR_SUBMISSION='/mnt/datarun/submission'
export RMQ_VHOST='rabbitMQ_vhost_name'
export IP_MASTER='xxx.yyy.zz.aaa'
```

Values of these environment variables must be the same as what you defined in env.sh, they are used to connect to the master and read data from it.

• On your local computer, create a file list\_runners.txt containing the list of runners address address, the number of tasks you want to be run concurrently on each runner, the list of queues processed by the workers (at least one of each among L, H, celery), and the hard and soft time limit in seconds:

```
address_runner_1 number_task_runner_1 list_queues_1 hard_time_limit_1 soft_time_limit_1
address_runner_2 number_task_runner_2 list_queues_2 hard_time_limit_2 soft_time_limit_2
...
address_runner_3 number_task_runner_3 list_queues_3 hard_time_limit_3 soft_time_limit_3
```

#### Example:

```
134.158.75.112 2 L,celery 360 300
134.158.75.113 3 H 240 200
```

Note: If there is only one runner, go to the next line, otherwise, it wil believe there is no runner to install...

• From your local computer (you are still in script\_install folder!), run:

```
bash scp_runner_stratuslab.sh list_runners.txt scienceFS_private_key
```

As above, scienceFS\_private\_key is the file name (with absolute path) of the private key to connect to ScienceFS account. This will scp some files to the runners and configure them (by executing the script deploy runner stratuslab.sh)

You should now be ready to use datarun on stratuslab!

### B. Using images datarun\_master and datarun\_runner on openstack

### B1. Start one instance for the master and as many instances as you want for the runners.

Use the image datarun\_master for the master and datarun\_runner for runners.

### B2. Go to the script\_install directory and stay there while configuring the master and runners.

#### **B3.** Configure master

- 1. Ssh to the instance
- 2. Go to /home/datarun/script\_install
- 3. Run bash deploy\_master\_from\_image.sh

### **B4.** Configure runners

• On your local computer, create a file list\_runners.txt containing the list of runners address address, the number of taskss you want be run concurrently on each runner, the list of queues processed by the workers (at least one of each among L, H, celery), and the hard and soft time limit in seconds:

```
address_runner_1 number_task_runner_1 list_queues_1 hard_time_limit_1 soft_time_limit_1 address_runner_2 number_task_runner_2 list_queues_2 hard_time_limit_2 soft_time_limit_2 ... address_runner_3 number_task_runner_3 list_queues_3 hard_time_limit_3 soft_time_limit_3
```

#### Example:

```
134.158.75.112 2 L,celery 360 300
134.158.75.113 3 H 240 200
```

- Run:
  - :: bash scp\_runner\_from\_image.sh list\_runners.txt

This will configure the runners (by executing the script deploy\_runner\_from\_image.sh). Check that the sciences disk has been correctly mounted (ssh to the instance and check if /mnt/datarun is not empty), sometimes it fails...

### C. How to install missing packages on runners

If the package can be installed with pip, run: runners\_install {list\_runner.txt} {package name} with {list\_runner.txt} being the file mentionned (A and B sections) specifying runners. It is going to run on each runner the following pip install {package\_name}

**FIVE** 

### **TESTS**

# for django tests

Run: python manage.py test

# for local celery tests

#### Run in one terminal:

```
cd test_files; bash local_test1.sh
```

#### Run in another terminal:

```
cd test_files; bash local_test2.sh -d
```

It creates a database, start celery workers, and run tests from test\_files/test\_workflow.py file.

If two 'Oh yeah' are printed, tests are ok!

### for tests on stratuslab

### Run:

```
cd test_files
bash stratuslab_test.sh master_address username password
```

with master\_address being the master server address (e.g., onevm-81.lal.in2p3.fr), username being a datarun user, and password its password.

It runs tests from test\_files/test\_workflow.py file.

If two 'Oh yeah' are printed, tests are ok!

24 Chapter 5. Tests

SIX

# **HOW TO DEAL WITH MIGRATIONS?**

If you modify the app models, you'll need to migrate the database.

- 1. modify runapp/models.py
- 2. run python manage.py makemigrations which will create a migrations file in runapp/migrations/
- 3. apply the migration with python manage.py migrate
- 4. add the migrations file to your git and commit both the modified runapp/models.py and migrations file (so that other contributors can have the migration history)

# **SEVEN**

# **INDICES AND TABLES**

- genindex
- modindex
- search

### PYTHON MODULE INDEX

```
r
runapp.models,7
runapp.views,9
t
test_files.post_api,12
```

30 Python Module Index

C custom_post_split() (in module test_files.post_api), 12 CustomSplitTrainTest (class in runapp.views), 9	Submission (class in runapp.models), 7 SubmissionFold (class in runapp.models), 8 SubmissionFoldDetail (class in runapp.views), 11 SubmissionFoldLightList (class in runapp.views), 11 SubmissionFoldList (class in runapp.views), 12
get() (runapp.views.RawDataList method), 10 get() (runapp.views.SubmissionFoldDetail method), 11 get() (runapp.views.SubmissionFoldLightList method),	T test_files.post_api (module), 12
P	
post() (runapp.views.CustomSplitTrainTest method), 9 post() (runapp.views.GetTestPredictionList method), 9 post() (runapp.views.GetTestPredictionNew method), 10 post() (runapp.views.RawDataList method), 10 post() (runapp.views.SplitTrainTest method), 11 post() (runapp.views.SubmissionFoldList method), 12 post_data() (in module test_files.post_api), 14 post_split() (in module test_files.post_api), 14 post_submission_fold() (in module test_files.post_api), 14	
R	
RawData (class in runapp.models), 7 RawDataList (class in runapp.views), 10 runapp.models (module), 7 runapp.views (module), 9	
S	
save_files() (in module runapp.views), 12	

SplitTrainTest (class in runapp.views), 11